EARLY DRAFT

Graph-Interpreter a scheduler of DSP/ML nanoApps

Contents

Use-cases	2
Overview	3
Implementation	4
Details	
Graph Text	5
nanoApp manifests	9
Platform manifest	10
Digital manifest	11
Graph interfaces manifests	12
Data types	16
List of installed nanoApps	18
List of app's callbacks	18
Embedded scripts	19
Node design	20

Use-cases

Graph-Interpreter is a scheduler of DSP/ML nanoApps designed with three objectives:

1. Accelerate time to market

For system integrators and OEM: develop complex DSP/ML stream processing. Go fast from prototypes validated on a computer to final tuning steps on board, by loading a graph of computing nodes without device recompilation.

2. NanoApps repositories

Provide to the nodes an opaque interface of the platform memory hierarchy. Arrange the data flow is translated in the node desired formats. Prepare the conditions where node (nanoApps) will be delivered in ciphered binary format.

3. Portability, scalability

Use the same stream-based processing methodology from devices using 1kBytes of internal RAM to multiprocessor heterogeneous architectures.

Use-case examples:

1. Tuning the IO interfaces of closed embedded systems


A block of Flash is reserved for the graph in a device. The graph implements a cascade of ML algorithms from analog sensing. The results are sent to the main application. The system integration consists in tuning the levels before data is shared with the application. A node is in charge of rescaling and resampling the input data rate for the next computing nodes in the graph. The system integrator updates the rescaler node and a debug script to trigger a GPIO based on level detection. The flash is updated without recompilation.

2. Tuning the algorithms of closed embedded systems

A node incorporates filters and detection thresholds, the system integrator updates the parameters of the node without recompilation. The memory mapping of the node can also be tuned or the dispatching of tasks assigned to other processors for performance optimization.

Overview

An example of computing graph is given in the picture below. The "**nodes**" (or called "**nanoApps**") are processing data provided through "**arcs**". Each arc's stream is characterized by its conveyed **data format** (raw format, number of channels, interleaving options, time-stamps, sampling-rate, frame size).



Graph of nodes for stream-based computing


The nodes at the boundary of the graph are called "**IOs**" (as Input / Output ports). The IOs are characterized by the physical **domain** of operation (image, audio, motion sensor, GPIO, connexion the application), the commander / servant protocol used with the platform **AL** (platform abstraction layer), and the FIFO buffer declaration (buffer declared inside or outside of the graph). When IOs are exchanging data they call functions in the list of platform AL functions with an index named **IO_AL_idx**.

A **platform** is characterized by the list of software and hardware IO interface the graph can use with the IO_AL_idx index, by the list of processors and their **memory banks** pre-reserved for the execution of the graph, by the list of the nodes pre-installed before graph execution. The details of a platform, nodes and IOs are recorded in respective "**manifests**".

The graph description incorporates the **presets** and **parameters** of the nodes to use at graph reset time. When the parameter and states needs to be exchanged dynamically during the graph execution a **script** (see picture) can be coupled before/after the execution of each node. The scripts consist in a compact **byte-code** language similar to the ones of old pocket calculators. A **global script** can be used for the interactions with the application (specific parameter settings during use-case transitions). A graph be reused as a **sub-graph** of a more complex graph.

Implementation

The graph to be interpreted is coded as a **binary graph** resulting from the "compilation" of the graph in text format (picture below). The graph compiler is a tool executed offline on a computer, it receives the characteristics of the platform, nodes and IOs in manifests.



The Graph Interpreter is used from two interfaces: one from the application and one to notify data move on IOs are finished.

The first interface is: void arm_graph_interpreter (uint32_t command, arm_stream_instance_t *instance, uint8_t *data, uint32_t size)
Where "command" tells to reset the graph, execute it, check boundary IOs filling state to move data in/out, set parameters. Instance is the memory allocated for the execution of the graph: a structure of pointers to the binary graph, to the installed nodes, to the AL stream interfaces functions (indexed with IO_AL_idx), some debug control fields.

The other interface is the call-back used to notify the end data moves with IOs: void arm_graph_interpreter_io_ack (uint8_t IO_AL_idx, uint8_t *data, uint32_t data_size)

The parameters of this function tell the "data" pointer with an amount of "size" bytes have been exchanged on the graph boundary with the AL interface indexed by IO_AL_idx. This function will read the binary graph information to find which **arc circular buffer descriptor** needs to be updated with this data move.

The graph interpreter the platform AL (abstraction layer) to manage the IO data moves, read the time or a counter, have access to a short list of critical DSP/ML subroutines optimized for the instruction-set of the platform and some functions of the standard library (memory allocation, math).

0

Details

Graph Text

Example of graph

```
-----
   Stream-based processing using a graph interpreter :
                                                                  CORRESPONDING BINARY GRAPH:
   The main script receives a code for the implementation of :
       - The ADC detection is used to toggle a GPIO
                                                                  0x00000091,
   0x00000000,
                                                                  0x00009123,
                                                                  0x00000010,
                                                                  0x00000006,
set_file_path 0 ./
set_file_path 1 ../
                                                                  0x00000001,
0×000000FF
set_file_path
                                                                  0x00000000,
                                                                  0xFFFFFFF
{\tt format\_frame\_length}
                    8
                                                                  0xFFFF3000,
format
                                                                  0x00000000,
format_frame_length
                                                                  0xFFFFFFF,
stream io
stream_io
stream_io_hwid
stream_io_format
                    a
                                                                  0xFFFFFFF
                                                                  0xfffffff,
                          ; io_platform_data_in_0.txt
                                                                  0xFFFFFFF,
                                                                  0xFFFFFFF
                                                                  0xFFFFFFF,
stream_io
stream_io_hwid 7
stream_io_format 1
                          ; io_platform_gpio_out_0.txt
                                                                  0xFFFFFFF,
                                                                  0xFFFF3802
;------
                                                                  0x00000000,
script 0
   script_code
2 h16; 2002 0001
                                                                  0xFFFFFFF
                           movi int16 r0 1
                                                                  0xFFFF1803,
      1 h16; e810
                           equ r0,#0
                                                                  0x00000000,
      1 h16; 0381
                           ccallsys 1
                                                                  0x22000008
      1 h16: C000
                           ret
                                                                  0x467A0000.
_end_______
                                                                  0x00000003,
                                                                  0x2200000C,
node arm_stream_filter 0
                                                                  0x467A0000
                                                                  0x00000004,
                        ; Q15 filter
; for debug
; TCM = VID5
; SRAM1
   node_preset
                                                                  0x22000008,
   node_malloc_E 1
node_map_hwblock 1 5
                                                                  0x0000001F
                                                                  0x00000000
   ..oue_map_swap 1 3 node_parameters
                                                                  0x00000003,
                                                                  0x00030000,
                          TAG = "all parameters"
      1 u8; 0
                                                                  0x05900004
      1 u8; 2
1 u8; 1
                           Two biquads
                                                                  0xAD020200.
                                                                  0x90B19261,
                           postShift
      5 s16; 9315, 14928, 9315, 25576, -11147,
                                                                  0x02020005
      5 s16; 9315, 5736, 9315, 9328, -26591,
                                                                  0x000261AD,
                                                                  0x01020102,
    _end_
                                                                  0x90B17100,
= =
!------
                                                                  0x00029801.
node arm_stream_detector 0 ; arm_stream_detector
                                                                  0x48010000
;----- LAST SECTION OF THE GRAPH-----
                                                                  0x00000090,
                                                                  0x00300007
arc_section
                                                                  0x12310002,
arc_input 0 arm_stream_filter
                                                                  0x12311D28,
arc_output 1 arm_stream_detector 0 1 0
                                                                  0xD47563E8.
                                                                  0x0B341231,
arc arm_stream_filter 0 1 0 arm_stream_detector 0 0 0
                                                                  0x24701231,
arc_map_hwblock 0
                                                                  0x00009821,
```

Syntax of graphs

Graph scheduler control

Tags	Parameters	Comments
	(type)	
graph_location	int	0: location of the binary graph is all in ram (default)
		1: keep the graph in Flash and copy in RAM the portion starting from the node linked-list
		2: keep the graph in Flash and copy in RAM the portion starting from the arc descriptors
		3: the graph is already in RAM provided by the application
debug_script_fields	int	LSB set means "call the debug script before each nanoAppsRT is called"
		bit 1 (2) set means "call the debug script after each naonoAppsRT is called"
		bit 2 (4) set means "call the debug script at the end of the loop"
		bit 3 (8) set means "call the debug script is called when starting the graph scheduling"
		bit 4 (16) set means "call the debug script is called when returning of the graph
		scheduling"
		no bit is set (default) the debug script is not called (default 0)
scheduler_return	int	1: return to caller after each SWC calls
		2: return to caller once all SWC are parsed
		3: return to caller when all SWC are starving (default 3)
allowed_processors	int	bit-field of the processors alloed to execute this graph, (default = 1 main processor)
graph_map_hwblock	0	index of the memory block VID indexes where to map the graph. Default VID's is 0 internal
		RAM
set_file_path	Int String	index and its file path, used for sub graphs and scripts

Graph stream formats

Tags	Parameters (type)	Comments
format	int	index used to start the declaration of a new format
format raw data	int	raw data of this format (17 : S16 is the default)
format frame length	int	frame length in number of bytes (default :1)
format interleaving	int	0 means interleaved data, 1 means deinterleaved data by packets of "frame size"
format nbchan	int	number of channels in the stream (default 1)
format time stamp	int	time-stamp format 0:none, 1:absolute time-stamp, 2:relative time, 3:simple counter
format time stamp size	int	0:16bits 1:32bits 2:64bits (see "STREAM TIME16D" for example)
format sdomain	int	subdomain type (for example see stream unit physical used for analog sensors)
_		qeneral (a)synchronous sensor + rescaling, remote data, compress
		audio in microphone, line-in, I2S, PDM RX
		audio out line-out, earphone / speaker, PDM TX, I2S,
		gpio in generic digital IO , control of relay,
		gpio out generic digital IO , control of relay,
		motion accelerometer, combined or not with pressure and gyroscope
		2d in camera sensor
		2d out display, led matrix,
		analog in with aging control
		analog out D/A, position piezzo, PWM converter
		rtc ticks sent from a programmable timer
		user interface in button, slider, rotary button
		user interface out LED, digits, display,
		platform 3
		platform 2 platform-specific #2, decoded with callbacks
		platform_1 platform-specific #1, decoded with callbacks
format domain	float	IO DOMAIN defined in the platform IO manifest (0 means "any")
format sampling rate	int	To bothin defined in the pideform to manifest to means day
format audio mapping	int	thd
format motion mapping	int	tbd
format 2d height	int	tbd
format 2d width	int	tbd

format_2d_border	int	tbd

Graph main IOs

Tags	Parameters	Comments
	(type)	
stream_io	int	index used to start the declaration of a new IO
stream_io_format	int	index to the stream format (Index of the above table) (default #0)
stream_io_hwid	int	ID of the interface given in "files_manifests_computer" (default #0)
stream_io_setting1	int	setting word32 (SETTINGS_IOFMT2), the format depends on the IO domain (default #0)
stream io	int	index used to start the declaration of a new IO

Graph memory mapping split

Split the memory mapping to ease memory overlays between nodes and arcs

format : original memory bank ID

new ID to use in the node/arc declarations

start within the original ID length of the new memory bank

Tags	Parameters (type)	Comments
memory_mapping	Int int int int	ORIGINAL_ID NEW_ID START LENGTH

Graph debug trace

Tags	Parameters (type)	Comments

Subgraphs

```
subgraph name, used for name mangling of the nodes and arcs
path ID (set_file_path) and file name
list of indexes from "top_graph_interface" (or indexes if we are already in a subgraph)
memory_mapping partitions, list of VIDs used in the subgraph
subgraph
   sub1
                              ; subgraph name, used for name mangling
                              ; path and file name
   3 sub_graph_0.txt
                              ; 5 streaming interfaces data_in_0, data_out_0 ..
   5 i16: 0 1 2 3 4
   3 i16: 0 0 0
                              ; 3 partitions here assigned to VID0 : fast-working slow-working slow-static
Nodes of the graph
       node_parameters
                              ; node parameters example (default : no parameter)
                              ; Set_parameter : the array of parameters starts on 32bits-aligned addresses
                              ; The programmer must arrange the data are aligned with respect to the way parameters
are read in
                                  the nanoApp (using pointers to 8/16/32bits fields).
                              ; TAG= 0 "load all parameters"
           7 i8; 2 3 4 5 6 7 8 ; parameters
include 1 filter_parameters.txt ; path + text file-name using parameter syntax
       _end
```

Tags	Parameters	Comments
	(type)	
node_preset	1	parameter preset used at boot time, default = #0
node_malloc_E	12	"E" parameter used in "Memory Size Bytes", default = #0
node_map_hwblock	2 3	index of the memory block "node_mem" and the VID indexes from
		"procmap_manifest_xxxx.txt" where to map it. Default VID's is 0.
node_map_copy	2 3	copy the indexed "node_mem" to VID 3 (faster memory) before run
node_map_swap	2 3	swap the indexed "node_mem" to VID 3 (faster memory) before run, and
		restored after
node_trace_id	0	IO port used to send the trace
node_map_proc	0	execute this nanoApp on this processor (0: any possible, default)
node_map_arch	0	execute this nanoApp on this architecture (0: any possible, default)
node_map_rtos	0	execute this nanoApp on this thread index (0: any possible, default)
node_map_verbose	0	level of debug trace, default = #0
node_script	<0127>	index of the script to call before and after execution of this node

Scripting nodes of the graph

Example

```
SCRIPTING NODE IN GRAPHS (SCHEDULED LIKE OTHER NODES)
     Checks if the data it needs is available and returns to the scheduler
; Its single arc (TX) is always empty node arm_stream_script 1 ; instance index of arm_stream_script
                                           ; numer of registers used in this script , default 2
     script_registers 2
                                           ; numer of pointers used in this script , default 2 ; size of the stack in word64 (default = 0)
     script_pointers 2
                             12
     script stack
     script_mem_shared 1
script_mem_map 0
                                           ; Is it a private RAM(0) or can it be shared with other scripts(1) ; Memory mapping to VID #0 (default)
                                           ; this declaration creates the transmit arc of the script-node pointing to the stack/buffer area
     script_code
                                           ; movi int16 r0 1
          2 h16; 2002 0001
1 h16; e810
                                           ; equ r1,r0
          1 h16; 0381
                                           ; ccallsys 1
          1 h16; C000
                                           ; ret
     _end_
     script_assembler
pshc int8 1
                                           ; start of assembler language (@@@ TBD)
          gtr
           cjmp #1
          pshc int16
           .
cals readparam
          labl #1
          ret
    _end_
                                           ; node parameters and index to let the code addressing it
; Set_parameter : the array of parameters starts on 32bits-aligned addresses
; The programmer must arrange the data are aligned with respect to the way parameters are read in
; the nanoApp (using pointers to 8/16/32bits fields).
    node_parameters <ID2>
         1 i8; 0
7 i8; 2 3 4 5 6 7 8
                                           ; TAG= 0 "load all parameters"
; parameters
    node parameters <ID2>
         include 1 binary_code.txt ; path ID and file name
    _end_
end
```

```
        Tags
        Parameters (type)
        Comments

        script_registers
        2
        numer of registers used in this script, default 2

        script_pointers
        2
        numer of pointers used in this script, default 2

        script_stack
        12
        size of the stack in word64 (default = 0)
```

0

script_mem_shared	1	Is it a private RAM(0) or can it be shared with other scripts(1)
script_mem_map	0	Memory mapping to VID #0 (default) this declaration creates the transmit
		arc of the script-node pointing to the stack/buffer area

Shared scripts used for node control

Example

```
; COMMON SCRIPTS IN GRAPHS (AND SCRIPT ID IN THE NODE HEADER "SCRIPT_LWO")
;
; script instance #0 is the "main script" of the subgraph
script 0 ; index of the script, to be mapped to an index in the graph compiler

script_registers 2 ; same as arm_stream_script
script_pointers 2 ;
script_stack 12 ;
script_mem_shared 1 ;
script_mem_shared 1 ;
script_mem_map 0 ;

script_code ; start of byte-codes of the script
2 h16; 2002 0001 ;
1 f64; 3.14159265359 ;
1 h16; e810 ;
1 i8 ; 0 ; parameters embedded in the code and addressed with Labels
7 i8 ; 2 3 4 5 6 7 8 ;
end
```

Graph arcs

Tags	Parameters (type)	Comments
		ARC CONNECTED TO GRAPH INTERFACE
		in a subgraph the IDX interfaces are sequential 1,2,3 and documented like function parameters in the main graph the "top_graph_interface" have the indexes to use use in the first column
		IO-ID NAME INST IO FORMAT
arc input	1	input arc index #1 connected to "node name" instance #2 and its arc index #0, Format #0
_	node_name 2 0 0	_
arc output	2	output arc index #2 connected to "node name" instance #3 and its arc index #1, Format #0
	node_name 3 1 0	_
arc		ARC CONNECTION BETWEEN TWO NANOAPPS
		NAME INST IO FMT NAME INST IO FMT
	node1 1 2 0	arc between nodel instance #1 arc index #2, producer format #0 to node2 instance #3 and its arc
	node2 3 4 1	index #4, consumer format #1
arc_flow_error	1	#1 do something depending on domain when a flow error occurs, default #0 (no interpolation)
arc debug cmd	1	debug action "ARC INCREMENT REG", default = #0 (no debug)
arc debug reg	3	index of the 64bits result, default = #0
arc debug page	0	debug registers base address + 64bits x 16 registers = 32 word32 / page, default = #0
arc flush	0	control of register "MPFLUSH ARCW1" : forced flush of data in MProcessing and shared tasks
arc_extend_addr	1	address range extension-mode of the arc descriptor "EXTEND_ARCW2" for large NN models, default = #0 (no extension)
arc map hwblock	0	mapping VID index from "procmap manifest xxxx.txt" to map the buffer, default = #0 (VID0)
arc_jitter_ctrl	1.5	factor to apply to the minimum size between the producer and the consumer, default = 1.0 (no jitter)

nanoApp manifests

Identification

Tags	Parameters (type)	Comments
	ARM	developer name
	arm_stream_detector	node name

Graph parameters

Tags	Parameter	Comments
node nb arcs	1 1	nb arc input, output, default values "1 1"
node_arc_parameter	0	SWC with extra-large amount of parameters (NN models) will declare it with extra arcs
node_steady_stream	1	(0) the data flow is variable (or constant, default value :1) on all input and output arcs
node_same_data_rate	1	(0) the arcs have different data rates, (1) all arcs have the same data rate
node_use_dtcm	1	default 0 (no MP DTCM_LW2), 1: fast memory pointer placed after the arc format
node_use_arc_format	0	default 1 : the scheduler must push each arc format (LOADFMT_LW0_LSB)
node_mask_library	15	default 0 bit-field of dependencies to computing libraries
node_subtype_units	VRMS	triggers the need for rescaling and data conversion
node_architecture	0	arch compatible with (default: 0 = source code) to merge and sort for ARCHID_LW0
node_fpu_used	0	fpu option used (default 0: none, no FPU assembly or intrinsic)
node_use_unlock_key	1	a key-exchange protocol is initiated at reset time
node_node_version	101	version of the computing node
node stream version	001	version of the stream scheduler it is compatible with

Node memory allocation

```
memory allocation size in bytes =

A : memory allocation in Bytes (default 0)

+ B x nb_channels of arc(i) : addition memory as a number of channels in arc index i (default 0)

+ C x sampling_rate of arc(j) ; .. as proportional to the sampling rate of arc index j (default 0)

+ D x frame_size of arc(k) ; .. as proportional to the frame size used for the arc index k (default 0)

+ E x parameter from the graph ; optional field "malloc_E" during the node declaration in the graph, for example the number of pixels in raw for a scratch area (default 0)
```

Tags	Parameter	Comments
node_mem	2	start the declaration of a new memory block with index 2
node_mem_alloc	32	size = 32Bytes data memory, Static, Fast memory block
node_mem_nbchan	4 0	add in Bytes : 4 x nb of channels of arc 0
node_mem_sampling_rate	0.1 1	add in Bytes : 0.1 x sampling rate of arc 1
node_mem_frame_size	1 0	add in Bytes : 1 x frame size of arc 0
node_mem_alignement	4	4 bytes (default)
node_mem_retention	1	0 for a Static memory allocation, preserved along the execution (default) 1 for Working (or Scratch) area which can be reused and overlaid by other nodes 2 for memory to be preserved (Retention) after a platform reboot
node_mem_speed	2	0 for 'best effort' or 'no constraint' on speed access 1 for 'fast' memory selection when possible 2 for 'critical fast' section, to be in I/DTCM when available
node_mem_relocatable	1	Default 0 : not relocatable, 1: a command 'STREAM_UPDATE_RELOCATABLE' is sent to the node to update the pointer to this memory allocation
node_mem_dataOprog1	0	selection data / program

Node arcs configuration

```
memory allocation size in bytes =

A : memory allocation in Bytes (default 0)

+ B x nb_channels of arc(i) : addition memory as a number of channels in arc index i (default 0)

+ C x sampling_rate of arc(j) ; .. as proportional to the sampling rate of arc index j (default 0)

+ D x frame_size of arc(k) ; .. as proportional to the frame size used for the arc index k (default 0)

+ E x parameter from the graph ; optional field "malloc_E" during the node declaration in the graph, for ; example the number of pixels in raw for a scratch area (default 0)
```

all the nodes must have at least one TX-arc (even a dummy one) used to manage the lock field.

Tags	Parameter	Comments			
node_arc	2	start the declaration of a new arc with index 2			
node_arc_rx0tx1	0	followed by 0:input 1:output, default = 0 0 and 1 1			
node_arc_sampling_rate	{1 16000 44100}	sampling rate options (enumeration in Hz), default "any"			
node_arc_interleaving	0	multichannel intleaved (0, default), deinterleaved by frame-size (1)			
node_arc_nb_channels	{1 1 2}	options for the number of channels (default 1)			
node_arc_raw_format	{1 17}	options for the raw arithmetics computation format here STREAM_S16, , default values "1 S16"			
node arc frame length	{1 1 2 16}	options of possible frame size in number of sample (can mono or multi-channel)			
node_arc_frame_duration	options of possible frame_size in [milliseconds]				
		(one sample can mono or multi-channel), default is "any length"			
node arc sampling period s	{1 0.1 0.2 0.4}	sampling period options (enumeration in [second])			
node_arc_sampling_period_day	{1 0.25 1 7}	sampling period options (enumeration in [day])			
node arc sampling accuracy	0.8	sampling rate accuracy in percent			
node_arc_inPlaceProcessing	1 0	index of the output arc sharing the same interface buffer as one			
node_arc		input arc buffer (default: all output buffers are separated from the input buffers)			
		start the declaration of a new arc with index 2			

Platform manifest

The "VID" (Virtual Identifier) index is used to translate the graph memory map addresses to physical addresses. This is a memory plane used to have compact representation of 64bits addresses and to help multiprocessors pointing to the same physical addresses even if they have address translators.

The platform **digital manifest** gives the base address and sizes of the memory planes addressed with up to **8 IDs**, each memory plane has multiple VID corresponding to physical memory blocks. By convention the VID index 0 is used for the shared RAM holding the graph's arc FIFO descriptors (read and write index indexes to buffers).

A system integrator can avoid specifying the VID memory mapping and let the graph compiler manage. Tuning the performance means taking care of overlays, or arranging processors don't have simultaneous access to the same physical memory banks, and this is where VID indexes are used.

Paths

```
3
../../stream_platform/
../../stream_platform/windows/manifest/
../../stream_nodes/
```

Digital manifests

1 procmap_manifest_computer.txt path index + file name

List IO manifest files

```
10

;Path Manifest IO_AL_idx ProcCtrl clock-domain
1 io_platform_data_in_0.txt 0 1 0
1 io_platform_data_in_1.txt 1 1 0
1 io_platform_analog_sensor_0.txt 2 1 0
1 io_platform_motion_in_0.txt 3 1 0
1 io_platform_audio_in_0.txt 4 1 0
1 io_platform_audio_in_0.txt 4 1 0
1 io_platform_2d_in_0.txt 5 1 0
1 io_platform_clock 6 1 0
1 io_platform_ppio_out_0.txt 7 1 0
1 io_platform_gpio_out_0.txt 8 1 0
1 io_platform_data_out_0.txt 9 1 0
```

List of nodes manifests

0

Digital manifest

```
; Processor and memory configuration + default memory mapping
     1 1 9 number of architectures, number of processors, number of memory banks
                    base offset ID reference above
    - ID
                     virtual ID used in the graph for manual mapping, must stay below 99 for swap controls (see NodeTemplate.txt) 0=any/1=normal/2=fast/3=critical-Fast, static0/working1/retention2,
     - W
     - P
- H
                    shared0/private1,
DMAmemHW1
     Data0/Prog1/Both2
Size minimum sizes guaranteed per VID starting from @[ID]+offset below
Offset maximum offset from the base offset ID, (continuous banks means = previous size + previous offset)
    the memory is further split in the graph "top_memory_mapping" to ease mapping and overlays
     ID VID S W P H D
                                  Size offset from offsetID 95526 10 VIDO=DEFAULT
                                                      VIDO-DEFAULT flat memory bank, can overlap with the others SRAMO static, hand tuned memory banks
                1 0 0 0 0
                                 65526 10
30000 65536
                0 0 0 0 0
                                                      SRAM1 static
               0 1 0 0 0 0 0 0 1 0 0 0
                                15000 95536
256000 262144
                                                       SRAM1 working at application level
                                                      DDR working at application level
DTCM Private memory of processor 1
Retention memory
         5 3 1 1 0 0
10 0 2 0 0 0
                                1024 262144
1024 524288
             0 0 0 0 0 0 3 1 1 0 1
                              200000 10
16384 0
                                                    Data in Flash
ITCM Private memory of processor 1
         20
    ; all architectures
          all processors (processor IDs >0)
          ;-----
                          processor ID, boolean "I am the main processor" allowed to boot the graphs
Bit-field computation firmware extensions, on top of the basic one, embedded in Stream services
EXT_SERVICE_MATH 1, EXT_SERVICE_DSPML 2, EXT_SERVICE_AUDIO 3, EXT_SERVICE_IMAGE 4
```

0

Graph interfaces manifests

The concept of Domains is used to select specific parameters (analog, audio, 2D, motion).

Parameters are set from a list of "options": from list or from a range.

Example of IO manifest. The file starts with the name and domain of the IO, followed by "options" corresponding to the physical domain.

Options syntax

An option can have several fields each in the list or the range format. The separation of fields is made with "{" and "}", the first integer selects the format of the field.

```
options sets: { index list } { index list }

when the list has one single element "X", this is the value to consider: {X} <=> {1 X} <=> X

when index == 0 it means "any", the list can be empty, the default value is not changed from reset

when index > 0 the list gives the allowed values the scheduler can select

The Index tells the default "value" to take at reset time and to put in the graph
the combination of index give the second word of stream_format_io[]

when index < 0 a list of triplets follows to describe a combination of data intervals: A1 B1 C1 A2 B2 C2 ...
A is starting value, B is the increment step, C is the included maximum value
The absolute index value selects the default value in this range
```

10 manifest Header

```
io_platform_sensor_in_0
                                              ; IO name for the tools
                                              ; domain name, among the list below :
analog in
domain name
                                           description and examples
                                          (a)synchronous sensor , electrical, chemical, color, .. remote data microphone, line-in, I2S, PDM RX line-out, earphone / speaker, PDM TX, I2S, generic digital IO , control of relay, generic digital IO , control of relay,
general
audio_in
audio out
gpio_in
gpio out
motion
2d in
                                           accelerometer, combined or not with pressure and gyroscope
                                           camera sensor
                                           display, led matrix,
2d_out
                                          with aging control
D/A, position piezzo, PWM converter
ticks sent from a programmable timer
button, Silder, rotary button
LED, digits, display,
platform-specific #x, decoded with callbacks
analog in
analog_out
user_interface_in
user_interface_out
platform_x
```

IO configuration

Tags	Parameter	Comments
io_commander0_servant1	1	commander=0 servant=1 (default is servant) IO stream are managed from the graph scheduler with the help of one subroutine per IO using the template: typedef void (*p_io_function_ctrl) (uint32_t command, uint8_t *data, uint32_t length); The "command" parameter can be: STREAM_SET_PARAMETER, STREAM_DATA_START, STREAM_STOP, STREAM SET BUFFER.
		And one subroutine for all IOs in charge of acknowledge the end of the data move, to update the circular buffer, manage overflows. This subroutine can be called from ISR void arm graph interpreter_io_ack (uint8 t fw_io_idx, uint8 t *data, uint32_t data_size); Where fw_io_Idx is the index given in "top_manifest_xxxx.txt"
		When the IO is "Commander" it calls arm_graph_interpreter_io_ack() when data is read When the IO is "Servant" the scheduler call p_io_function_ctrl(STREAM_DATA_START,) to ask for
io buffer allocation	2 1	data move. Once the move is done the IO driver calls arm graph interpreter io ack() default is 0, which means the buffer is declared outside of the graph

		The floating-point number is a multiplication factor of the frame size (here 2 frames), the buffer size is computed with rounding $(n = floor(X+0.5))$			
		When more than one byte are exchanged, the IO driver needs a temporary buffer. This buffer can be allocated "outside(0)" by the IO driver, or ">1" during the graph memory mapping preparation The memora mapping of this allocation is decided in the graph and can be in general-purpose or any RAM "0" or specific memory bank for speed reason or reserved for DMA processing, etc			
io direction rx0tx1	1	direction of the stream 0:input 1:output from graph point of view			
io raw format	S16	options for the raw arithmetics computation format here STREAM S16			
io interleaving	1	multichannel intleaved (0), deinterleaved by frame-size (1)			
io nb channels	1	options for the number of channels			
io frame length	{1 1 2 16 }	options of possible frame size in number of sample (can mono or multi-channel).			
io_frame_duration	{1 10 22.5}	options of possible frame size in [milliseconds]. The default frame length is 1 sample			
io_subtype_units	VRMS	depending on the domain. Here Units_Vrms of the "general" domain (0 = any or underfined)			
io_subtype_multiple	{DPS GAUSS}	example for multi domain sensor : motion can have up to 4 data units for accelerometer, gyroscope, magnetometer, temperature			
io_power_mode	0	to set the device at boot time in stop / off (0) running mode(1): digital conversion (BIAS always powered for analog peripherals) running mode(2): digital conversion BIAS shut-down between conversions Sleep (3) Bias still powered but not digital conversions			
io_position meter	1.1 -2.2 0.01	unit and relative XYZ position with the platform reference point			
io_euler_angles	10 20 90	Euler angles with respect to the platform reference orientation, in degrees			
io_sampling_rate	{1 16000 44100 48000}	sampling rate options (enumeration in Hz)			
io_sampling_period_s	{1 1 60 }	sampling period options (enumeration in [second])			
io_sampling_period_day	{1 0.25 1 7}	sampling period options (enumeration in [day])			
io_sampling_rate_accuracy	0.1	in percentage			
io_time_stamp_format	{1 1}	0 no time-stamp, 1 absolute time, 2 relative time from last frame, 3 frame counter			
io_time_stamp_length	{1 1}	0/1/2/3 corresponding to 16/32/64/64 bits time formats (default : STREAM_TIME32)			

Domain-specific IO configuration

general

Tags	Parameter	Comments
io_commander0_servant1	1	commander=0 servant=1 (default is servant) IO stream are managed from the graph scheduler with the help of one subroutine per IO using the template: typedef void (*p_io_function_ctrl) (uint32_t command, uint8_t *data, uint32_t length); The "command" parameter can be: STREAM_SET_PARAMETER, STREAM_DATA_START, STREAM_STOP, STREAM_SET_BUFFER.
		And one subroutine for all IOs in charge of acknowledge the end of the data move, to update the circular buffer, manage overflows. This subroutine can be called from ISR void arm_graph_interpreter_io_ack (uint8_t fw_io_idx, uint8_t *data, uint32_t data_size); Where fw_io_idx is the index given in "top_manifest_xxxx.txt"
		When the IO is "Commander" it calls arm graph_interpreter_io_ack() when data is read When the IO is "Servant" the scheduler call p_io_function_ctrl(STREAM_DATA_START,) to ask for
io_buffer_allocation	2.1	data move. Once the move is done the IO driver calls arm graph interpreter io ack() default is 0, which means the buffer is declared outside of the graph The floating-point number is a multiplication factor of the frame size (here 2 frames), the buffer size is computed with rounding (n = floor(X+0.5))
		When more than one byte are exchanged, the IO driver needs a temporary buffer. This buffer can be allocated "outside(0)" by the IO driver, or ">1" during the graph memory mapping preparation The memora mapping of this allocation is decided in the graph and can be in general-purpose or any RAM "O" or specific memory bank for speed reason or reserved for DMA processing, etc
io_direction_rx0tx1	1	direction of the stream 0:input 1:output from graph point of view
io_raw_format	S16	options for the raw arithmetics computation format here STREAM_S16
io_interleaving	1	multichannel intleaved (0), deinterleaved by frame-size (1)
io_nb_channels	1	options for the number of channels

audio_in

Tags	Parameter	Comments				
io_nb_channels	{1 1 2}	options for the number	of chann	iels		
io_channel_mapping	1	mono (Front Left), 18 c	hannels	can be controlle	d :	
		Front Left	FL	bit0		
		Front Right	FR	1		
		Front Center	FC	2		
		Low Frequency	LFE	3		
		Back Left	BL	4		
		Back Right	BR	5		
		Front Left of Center	FLC	6		
		Front Right of Center	FRC	7		
		Back Center	BC	8		
		Side Left	SL	9		
		Side Right	SR	10		
		Top Center	TC	11		
		Front Left Height	TFL	12		
		Front Center Height	TFC	13		
		Front Right Height	TFR	14		
		Rear Left Height	TBL	15		
		Rear Center Height	TBC	16		
l		Rear Right Height	TBR	17		Į.

io_analog_gain	{1 0 12 24 }	analog gain (PGA)
io_digital_gain	{-1 -12 1 12 }	digital gain range
io_hp_filter	{1 1 20 50 300 }	high-pass filter (DC blocker) ON(1)/OFF(0) followed by cut-off frequency options

audio out

Tags	Parameter	Comments			
io_subtype_units	87	Units is [mV]			
io_analog_scale	1400	1400nV is corresponding to full-scale with the default setting			
io_sampling_rate	{1 16000 44100 48000}	sampling rate options (enumeration in Hz)			
io_nb_channels	{1 1 1 2	; multichannel intleaved (0), deinterleaved by frame-size (1) + options for the number of channels			
io channel mapping	1	mono (Front Left), 18 channels can be controlled :			

gpio_in gpio_out

control of time-stamps, sampling rate,

motion

```
{\tt io\_sampling\_rate}
                             1 16000 44100 48000
                                                        ; sampling rate options (enumeration in Hz)
io_sampling_period_s
                            1 0.01 0.02 0.04; sampling period options (enumeration in [second])
io_sampling_accuracy
                                                 ; sampling rate accuracy in percent
                                                                                                                   /* only accelerometer *
/* only gyroscope */
/* only magnetometer */
/* A + G */
/* A + M */
                                                 ; subtype_motion aXg0m0 1
                                                                                                                       only accelerometer */
                                                    subtype_motion a0gXm0 2
subtype_motion a0g0mX 3
                                                   subtype_motion aXgXm0 4
subtype_motion aXg0mX 5
                                                    subtype_motion a0gXmX 6
subtype_motion aXgXmX 7
                                                                                                                    /* G + M */
/* A + G + M */
io_motion_format 4
                                                  ; imu_channel_format
io_motion_averaging \, acc \, 1 \, 1 4 16 32; averaging in nb of samples io_motion_averaging \, gyro \, 1 \, 1 4 16 32; averaging in nb of samples
io high pass
                 0 /1
                                                 ; remove clicks
io_DC-canceller
```

2d_in

io_zoom_area

```
io raw format 2d
                                                    (U16 + RGB16) (U8 + Grey) (U8 + YUV422)
io_synchronize with IR transmitter https://developer.android.com/reference/android/hardware/HardwareBuffer io_frame rate per second
io_exposure time io_image size
                                                    The amount of time the photosensor is capturing light, in seconds.
                                                 portrait, landscape, barcode, night modes

Amplification factor applied to the captured light. 1.0 is the default gain; more than 1.0 is brighter; less than 1.0 is darker.

Temperature parameter when using the regular HDRP color balancing.

Tint parameter when using the regular HDRP color balancing.

Color Filter Array pattern for the colors.

ients Custom RGB scaling values for white balance, used only if EnableWhiteBalanceRGBCoefficients is selected.

ioefficients Enable using custom RGB scaling values for white balance instead of temperature and tint.

Assumes the camera is looking at a white reference, and calibrates the WhiteBalanceRGBCoefficients. Refer to the API for more
io_modes
io_Gain
io WhiteBalanceColorTemp
io_WhiteBalanceColorTint
io MosaicPattern
io_WhiteBalanceRGBCoefficients
io_EnableWhiteBalanceRGBCoefficients
io_Auto White Balance Assumes the
details.
io_time-stamp (none)
io_wdr;
io_watermark;
                                                    wide dynamic range flag (tuya) watermark insertion flag (tuya)
                                                    image format (portrait, panoramic)
motion detection sensitivity (low, medium, high)
+ {center pixel (in %) radius}, {}, {}
io_flip;
io_night_mode;
io_detection_zones;
io_focus_area
io_auto exposure on focus area
io_focus_distance
                                                     forced focus to infinity or xxx meters
io get distance
                                                    from focus area
```

io_time_stamp;
io_light_detection;
io_jpeg_quality
io_sound_detection;
io_other_sensors;

detection time-stamp format

sound level humidity, battery%

2d_out

8b backlight brightness control

0

Data types

Raw data types

```
STREAM_DATA_ARRAY 0 see stream_array: [ONNNTTOO] 0, type, nb STREAM_S1 1 S, one signed bit, "0" = +1
                                                                                                       one bit per data
                            one bit unsigned, boolean
STREAM U1
STREAM_S2
STREAM_U2
                            SX
                                                                                                       two bits per data
                        4 XX
STREAM_Q1
STREAM S4
                        5 Sx ~stream_s2 with saturation management
6 Sxxx
7 xxxx
                                                                                                       four bits per data
STREAM_U4
STREAM_Q3
STREAM_FP4_E2M1
STREAM_FP4_E3M0
STREAM_S8
                            Sxxx
                           Seem micro-float [8 .. 64]
                            Seee [8 .. 512]
Sxxxxxxx
                      10
                       11
                                                                                                       eight bits per data
STREAM_S8
STREAM_U8
STREAM_C1
STREAM_CHAR
STREAM_FP8_E5M2
STREAM_FP8_E5M2
STREAM_U16
STREAM_U16
STREAM_U15
STREAM_U16
                            xxxxxxxx ASCII char, numbers..
Sxxxxxxx arithmetic saturation
                       14
                            xxxxxxx
                            Seeeemmm NV tiny-float [0.02 .. 448]
Seeeeemm IEEE-754 [0.0001 .. 57344]
                            2 bytes per data
                       19
                            Sxxxxxxx.xxxxxxx arithmetic saturation
                            Seeeeemm.mmmmmmm half-precision float
STREAM BF16
STREAM Q23
STREAM Q23 32
STREAM S32
STREAM U32
                       21
                            Seeeeee.mmmmmmmm bfloat
                            Sxxxxxxx.xxxxxxx 24bits
                                                                                                        3 bytes per data
                       23
                            4 bytes per data
                            STREAM_032
STREAM_Q31
STREAM_FP32
STREAM_CQ15
STREAM_CFP16
STREAM_S64
                            2.6
                       28
                            Sxxxxxxx.xxxxxxx Sxxxxxxx.xxxxxxx (I Q)
Seeeeemm.mmmmmmmm Seeeeemm.mmmmmmmmm (I Q)
                       29
30
                            8 bytes per data
STREAM_U64
STREAM_Q63
STREAM_CQ31
STREAM_FP64
                       31
                       33
                            Seeeeee.eeemmmmm.mmmmmmm ... double
STREAM CFP32
STREAM FP128
STREAM CFP64
STREAM FP256
STREAM FP256
                       35
                            36
37
                            Seeeeeee.eeeeeee.mmmmmmm ... quadruple precision fp64 fp64 (I Q)
                                                                                                     16 bytes per data
                           38
STREAM_TIME16D
STREAM_TIME32
STREAM_TIME32D
STREAM_TIME32D
STREAM_TIME5TMP
STREAM_TIME64
STREAM_TIME64MS
                       40
                            STREAM_TIME64MS 45
STREAM_TIME64MS 46
STREAM_WGS84 47
STREAM_HEXBINARY 48
STREAM_BASE64 49
STREAM_BASE64 49
STREAM_STRING8 50
UTF-8 lower case hexadecimal byte str. STREAM_STRING8 50
UTF-8 string of char terminated by 0
STREAM_STRING16 51
UTF-16 string of char terminated by 0
```

Physical units (RFC8428 RFC8798)

```
        Physical units (RFC8428 RF

        STREAM_SUBT_ANA_ANY
        0

        STREAM_SUBT_ANA_METER
        1

        STREAM_SUBT_ANA_KGRAM
        2

        STREAM_SUBT_ANA_GRAM
        3

        STREAM_SUBT_ANA_GRAM
        4

        STREAM_SUBT_ANA_AMPERE
        5

        STREAM_SUBT_ANA_KELVIB
        6

        STREAM_SUBT_ANA_CANDELA
        7

        STREAM_SUBT_ANA_HERTZ
        9

        STREAM_SUBT_ANA_HERTZ
        9

        STREAM_SUBT_ANA_RADIAN
        10

        STREAM_SUBT_ANA_RADIAN
        10

        STREAM_SUBT_ANA_NEWTON
        12

        STREAM_SUBT_ANA_PASCAL
        13

        STREAM_SUBT_ANA_DOULE
        14

        STREAM_SUBT_ANA_WATT
        15

        STREAM_SUBT_ANA_COULOMB
        16

                                                                                                                                                                                                       kilogram
gram*
                                                                                                                                                           g
                                                                                                                                                                                                         second
                                                                                                                                              5 A
6 K
7 cd
8 mol
                                                                                                                                                                                                         kelvin
                                                                                                                                                                                                         candela
                                                                                                                                                                                                         mole
                                                                                                                                                                                                         hertz
                                                                                                                                                            Ηz
                                                                                                                                                                                                          radian
                                                                                                                                                            sr
                                                                                                                                                                                                         steradian
                                                                                                                                                            N
                                                                                                                                                                                                         newton
                                                                                                                                                           Рa
                                                                                                                                                                                                        pascal
                                                                                                                                                            J
                                                                                                                                                                                                           ioule
                                                                                                                                                                                                          watt
 STREAM_SUBT_ANA_COULOMB
STREAM_SUBT_ANA_VOLT
STREAM_SUBT_ANA_FARAD
STREAM_SUBT_ANA_OHM
STREAM_SUBT_ANA_SIEMENS
                                                                                                                                           16
17
                                                                                                                                                            C
                                                                                                                                                                                                        coulomb
                                                                                                                                                                                                         volt
                                                                                                                                           18
                                                                                                                                                                                                         farad
                                                                                                                                                           Ohm
S
                                                                                                                                           19
                                                                                                                                                                                                        ohm
siemens
  STREAM_SUBT_ANA_WEBER
STREAM_SUBT_ANA_TESLA
                                                                                                                                           21
                                                                                                                                                            Wb
                                                                                                                                                                                                         weber
                                                                                                                                                                                                           tesla
STREAM SUBT ANA TESLA
STREAM SUBT ANA HENRY
STREAM SUBT ANA CELSIUSDEG
STREAM SUBT ANA LUMEN
STREAM SUBT ANA LUMEN
STREAM SUBT ANA BQ
STREAM SUBT ANA GRAY
STREAM SUBT ANA GRAY
STREAM SUBT ANA KATAL
STREAM SUBT ANA KATAL
STREAM SUBT ANA CEBICMETER
STREAM SUBT ANA CUBICMETER
STREAM SUBT ANA CUBICMETER
STREAM SUBT ANA LITER
                                                                                                                                           23
                                                                                                                                                           Н
                                                                                                                                                                                                         henry
                                                                                                                                          24
25
                                                                                                                                                                                                          degrees Celsius
                                                                                                                                                            Cel
                                                                                                                                                            lm
                                                                                                                                                                                                         lumen
                                                                                                                                          26
27
                                                                                                                                                            lx
                                                                                                                                                                                                         lux
                                                                                                                                                              Bq
                                                                                                                                                                                                          becquerel
                                                                                                                                                            Gy
Sv
                                                                                                                                                                                                         gray
sievert
                                                                                                                                           28
                                                                                                                                           29
30
                                                                                                                                                            kat
                                                                                                                                                                                                         katal
                                                                                                                                                                                                          square meter (area)
                                                                                                                                           31
                                                                                                                                                            m2
STREAM SUBT ANA CUBICMETER STREAM SUBT ANA LITER STREAM SUBT ANA M PER S STREAM SUBT ANA W PER M S STREAM SUBT ANA CD PER M S STREAM SUBT ANA BIT STREAM SUBT ANA BIT STREAM SUBT ANA BIT PER S STREAM SUBT ANA BIT PER S STREAM SUBT ANA BIT PER S STREAM SUBT ANA LATITUDE STREAM SUBT ANA LATITUDE STREAM SUBT ANA LATITUDE
                                                                                                                                           32
                                                                                                                                                            m3
                                                                                                                                                                                                         cubic meter (volume)
                                                                                                                                                                                                       cubic meter (volume)
liter (volume)
meter per second (velocity)
meter per square second (acceleration)
cubic meter per second (flow rate)
liter per second (flow rate)*
watt per square meter (irradiance)
candela per square meter (luminance)
hit (information content)
                                                                                                                                           33
                                                                                                                                                            1
                                                                                                                                                          m/s
                                                                                                                                           35
                                                                                                                                                            m/s2
                                                                                                                                           36
37
                                                                                                                                                            m3/s
                                                                                                                                                            1/s
                                                                                                                                           38
                                                                                                                                                            W/m2
                                                                                                                                                            cd/m2
                                                                                                                                                                                                        bit (information content)
bit per second (data rate)
degrees latitude[1]
                                                                                                                                           40
                                                                                                                                                            bit
                                                                                                                                                            bit/s
                                                                                                                                           42
                                                                                                                                                           lat
                                                                                                                                                                                                         degrees longitude[1]
```

0

```
STREAM SUBT ANA PH
                                                                                          44 pH
                                                                                                                                  pH value (acidity; logarithmic quantity)
STREAM SUBT ANA PH
STREAM SUBT ANA DB
STREAM SUBT ANA DBW
STREAM SUBT ANA BSPL
STREAM SUBT ANA COUNT
STREAM SUBT ANA PER
STREAM SUBT ANA PERCENT
STREAM SUBT ANA PERCENTRH
                                                                                                                                   decibel (logarithmic quantity)
decibel relative to 1 W (power level)
                                                                                                     dВ
                                                                                                     dBW
                                                                                                                                 decibel relative to 1 W (power level)
bel (sound pressure level; log quantity)
1 (counter value)
1 (ratio e.g., value of a switch; [2])
1 (ratio e.g., value of a switch; [2])*
Percentage (Relative Humidity)
                                                                                                     Bspl
count
                                                                                          47
                                                                                          49
                                                                                          51
                                                                                                      %RH
                                                                                                                                   Percentage (remaining battery energy level) seconds (remaining battery energy level)
 STREAM_SUBT_ANA_PERCENTEL
STREAM_SUBT_ANA_ENERGYLEVEL
                                                                                          52
                                                                                                      %EL
                                                                                          53
                                                                                                     EL
                                                                                                    EL seconds (remaining battery energy level)

1/s 1 per second (event rate)

1/min 1 per minute (event rate, "rpm")*

beat/min 1 per minute (heart rate in beats per minute)

beats 1 (Cumulative number of heart beats)*

S/m Siemens per meter (conductivity)

B Byte (information content)

VA volt-ampere (Apparent Power)

Vas volt-ampere second (Apparent Energy)

var volt-ampere reactive (Reactive Power)

vars volt-ampere-reactive second (Reactive Energy)

I/m ioule per meter (Energy per distance)
 STREAM SUBT ANA 1 PER S
STREAM SUBT ANA 1 PER S
STREAM SUBT ANA 1 PER MIN
STREAM SUBT ANA BEAT PER MIN
STREAM SUBT ANA BEATS
STREAM SUBT ANA SIEMPERMETER
                                                                                          54
                                                                                          56
                                                                                          57
58
STREAM SUBT ANA SIEMPERMETER
STREAM SUBT ANA BYTE
STREAM SUBT ANA VOLTAMPERE
STREAM SUBT ANA VOLTAMPERESEC
STREAM SUBT ANA VAREACTIVE
STREAM SUBT ANA VAREACTIVESEC
STREAM SUBT ANA JOULE PER M
STREAM SUBT ANA JOULE PER M
STREAM SUBT ANA KG PER M3
                                                                                          59
                                                                                          61
                                                                                          63
                                                                                                     J/m
kg/m3
                                                                                                                                   joule per meter (Energy per distance) kg/m3 (mass density, mass concentration)
                                                                                          64
 STREAM SUBT ANA DEGREE STREAM SUBT ANA NTU
                                                                                          66
67
                                                                                                     deg
NTU
                                                                                                                                 degree (angle) *
Nephelometric Turbidity Unit
 dary Unit (rfc8798)
STREAM SUBT ANA MS
STREAM SUBT ANA MIN
STREAM SUBT ANA H
                                                                                       Description
                                                                                                                                                   SenML Unit
                                                                                                                                                                                             Scale Of: 1/1000
                                                                                          68 millisecond
69 minute
                                                                                                                                                                                                                                                                1ms = 1s \times [1/1000]
                                                                                                                                                                                        s
                                                                                                                                                                                                             60
                                                                                                                                                                                                                                         0
                                                                                                                                                                                                              3600
                                                                                                     hour
STREAM SUBT ANA H
STREAM SUBT ANA MHZ
STREAM SUBT ANA KW
STREAM SUBT ANA KW
STREAM SUBT ANA KVAR
STREAM SUBT ANA AH
STREAM SUBT ANA WH
STREAM SUBT ANA WH
STREAM SUBT ANA WH
STREAM SUBT ANA WH
STREAM SUBT ANA VARH
STREAM SUBT ANA VARH
STREAM SUBT ANA KVARH
STREAM SUBT ANA KVARH
                                                                                          71
                                                                                                     megahertz
                                                                                                                                                                                         Ηz
                                                                                                                                                                                                                                          0
                                                                                                     kilowatt
kilovolt-ampere
                                                                                                                                                                                                               1000
                                                                                           73
                                                                                                                                                                                         VA
                                                                                                                                                                                                              1000
                                                                                                                                                                                                                                          0
                                                                                          74
75
                                                                                                     kilovar
ampere-hour
                                                                                                                                                                                                             1000
3600
                                                                                          76
                                                                                                     watt-hour
                                                                                                                                                                                                              3600
                                                                                                                                                                                                                                          Λ
                                                                                                      kilowatt-hour
                                                                                                                                                                                                               3600000
                                                                                          78
                                                                                                     var-hour
                                                                                                                                                                                         vars
                                                                                                                                                                                                             3600
STREAM SUBT ANA KVARH
STREAM SUBT ANA KVARH
STREAM SUBT ANA KVARH
STREAM SUBT ANA KUB
STREAM SUBT ANA KIB
STREAM SUBT ANA KIB
STREAM SUBT ANA GB
STREAM SUBT ANA B PER S
STREAM SUBT ANA MB PER S
STREAM SUBT ANA MB PER S
STREAM SUBT ANA MB PER S
STREAM SUBT ANA MA
STREAM SUBT ANA MA
STREAM SUBT ANA MB
STREAM SUBT ANA PER
STREAM SUBT ANA MB
STREAM SUBT ANA MB
STREAM SUBT ANA MB
STREAM SUBT ANA MB
                                                                                                                                                                                                              3600000
                                                                                                      kilovar-hour
                                                                                                                                                                                         vars
                                                                                                     kilovolt-ampere-hour
                                                                                          80
                                                                                                                                                                                         VAs
                                                                                                                                                                                                              3600000
                                                                                                                                                                                                                                          0
                                                                                                     watt-hour per kilometer
kibibyte
                                                                                                                                                                                                             3.6
1024
                                                                                          82
                                                                                          8.3
                                                                                                     gigabyte
megabit per second
                                                                                                                                                                                                              1e9
                                                                                                   byteper second
megabyte per second
millivolt
million
                                                                                                                                                                                                             1000000
                                                                                          85
                                                                                                                                                                                         bit/s
                                                                                                                                                                                                             8000000
                                                                                                                                                                                         bit/s
                                                                                                                                                                                                             1/1000
                                                                                          88
                                                                                                     milliampere
                                                                                                                                                                                                             1/1000
                                                                                                     decibel rel. to 1 milliwatt
                                                                                                                                                                                        dBW
                                                                                          89
                                                                                                                                                                                                                                     -30
                                                                                                                                                                                                                                                           0 \text{ dBm} = -30 \text{ dBW}
                                                                                                                                                                                                             1e-9
                                                                                                     microgram per cubic meter millimeter per hour
                                                                                                                                                                                        kg/m3
m/s
                                                                                          90
                                                                                                                                                                                                                                         0
                                                                                                                                                                                                              1/3600000 0
                                                                                                     meterper hour
partsper million
                                                                                           92
                                                                                                                                                                                         m/s
                                                                                                                                                                                                             1/3600
                                                                                                                                                                                                                                         0
                                                                                           93
                                                                                                                                                                                                              1/100
                                                                                                     percent
                                                                                                      permille
                                                                                          95
                                                                                                                                                                                                             1/1000
                                                                                                                                                                                                                                          Ω
                                                                                                                                                                                                             100
1/1000
                                                                                                     hectopascal
                                                                                                                                                                                         Рa
 STREAM_SUBT_ANA_MM
STREAM_SUBT_ANA_CM
                                                                                                     millimeter
centimeter
                                                                                                                                                                                                                                         0
 STREAM_SUBT_ANA_KM
STREAM_SUBT_ANA_KM_PER_H
STREAM_SUBT_ANA_GRAVITY
                                                                                          99
                                                                                                      kilometer
                                                                                                                                                                                         m
                                                                                                                                                                                                             1000
                                                                                                                                                                                                                                         0
                                                                                        100
                                                                                                     kilometer per hour
                                                                                                                                                                                                              1/3.6
                                                                                                                                                                                                             9.81
                                                                                                                                                                                        m/s2
                                                                                                                                                                                                                                                                1g = m/s2 \times 9.81
                                                                                       101
                                                                                                     earth gravity
 STREAM SUBT ANA DPS
STREAM SUBT ANA GAUSS
STREAM SUBT ANA VPMS
STREAM SUBT ANA MVPGAUSS
                                                                                                     degrees per second
                                                                                                                                                                                                                                                        1dps = 1/s x 1/360

1G = Tesla x 1/10000

1Vrms = 1Volt (peak) x 0.707
                                                                                                                                                                                         1/s 360
Tesla 10-4
                                                                                       102
                                                                                        103
                                                                                                     Gauss
                                                                                       103 Gauss
104 Volt rms
105 Hall effect, mV/Gauss
                                                                                                                                                                                         Volt
                                                                                                                                                                                                            0.707
                                                                                                                                                                                        millivolt 1
```

List of installed nanoApps

```
; List of nodes
; List of node
```

List of app's callbacks

Use-case

Embedded scripts

A virtual machine with 6 registers, 6 pointers, loop counter and a stack. Instructions are coded with 2 bytes.

0

Node design

Calling sequence

The main CMSIS-Stream instance (the one located in the main process or processor) is called by the application to compute the amount of memory needed to execute the graph: the buffers of the arcs, the SWC instances of the graph, the buffers used for IOs (command "STREAM_MEMREQ" below).

In a second step, the application provides the memory pointers to the requested memory banks. The CMSIS-Stream instances are now allowed to activate of the IOs at the boundary of the graph, do the memory initialization of all SWC (command "STREAM RESET" below).

Finally, the application lets the graph being scheduled by CMSIS-Stream (command "STREAM_RUN" above).

The first control API has four parameters, three data parameters and a command with values: STREAM_MEMREQ: the application asks for the amount of memory needed to schedule the graph; the function returns the needed amount of memory for each memory bank (see "1.1.2 processor characteristics"). The parameters are:

- A function pointer to the firmware of the platform, in charge of the low-level abstraction of the hardware controls:
 - Returns the details of current processor: its index in the manifest table, its architecture and the FPU options
 - Call one on the three functions used to control the device drivers: "set", "start", "stop" (see "2) The graph boundaries")
 - o Read the time information, for example computed from a SYSTICK global counter.
- A pointer to the list of SWC entry points, and a pointer to their respective manifests (see "1.3 SWC manifests")
- A pointer to the "graph description text" to be compiled to "binary graph structure"
- a) STREAM_RESET: pointers memory banks are provided to "arm_stream()" which can initialize its instances and the SWC instances of the graph. In a similar way described for SWC (see "3.1.2 SWC parameter RESET") the application is providing to the CMSIS-Stream a callback mechanism. Each CMSIS-Stream instance is stored in the shared memory of "binary graph structure" with the format:
 - 7 offsets to the physical memory banks (see "1.1.2 processor characteristics"). This information lets the arc's buffer being address with indexes instead of physical pointers, it allows sharing the same arc's descriptors among processors having different memory address decoding (including arch64 processors).
 - Debug informations, the execution state of the instance, the current SWC under processing.
 - A 32bits-field of the graph IO ports to have look to. Most CMSIS-Stream instances will not be given access to
 the peripherals. Those indexes are used to address the platform IO manifest and checking the associated
 graph's ring buffers are not having flow problems.
 - A function pointer to the firmware of the platform (see above).
 - The list of SWC entry points
- **b) STREAM_RUN**: the graph of components is scheduled (the linked-list of the "binary graph structure" is parsed, see "3) Linked list of SWC")
- c) STREAM_END: command forwarded to each SWC to release memory allocated with stdlib.

CMSIS-Stream is scheduling the software components of a graph. The nodes of the graph are **software components** ("SWC") independent of the platform capabilities.

The graph description is a text file (example <u>here</u>) and is the result from the translation made in a GUI tool, using:

- a manifest of the platform (details on processors, memory, peripherals)
- a manifest of each SWC: description of the data formats of the interfaces

CMSIS-Stream is translating the graph description text file to a **binary graph structure**, with the help of the data in the manifests. This result is placed in shared memory area to all processes and processors.

This shared binary graph structure consists in:

- the linked list of arcs and nodes (the SWC) of the graph
- the arcs descriptors (read and write indexes to circular buffers)
- the memory of the CMSIS-Stream instances scheduled the graph.
- the structure describing the operations at the boundary of the graph (the graph "IOs")
- registers used to synchronize the different CMSIS-Stream instances, if any

Two entry-points

CMSIS-Stream has two entry-points, one for controling and asking for services, and a second one used as callback for notifications of data transfers :

```
void arm_stream (uint32_t command, PTR_INT ptr1, PTR_INT ptr2, PTR_INT ptr3);
void arm_stream_io (uint32_t fw_io_idx, void *data, uint32_t length);
```

The second control API (arm_stream_io) has three parameters: the index of the device driver calling this function, the base address of the buffer, the size of the buffer. The "index" is given in the platform IO manifest (see "1.2.4 The ID of the hardware port"). Data format and interleaving is described at "A.3.1 Data format fields common to all streams".

The description of the scheduling of the graph consists in:

- the content of the manifests of the platform and the manifests of the SWC
 - o paragraph below "1) Platform and SWC manifests"
- the way the IOs are sharing data with the ring buffers at the boundary of the graph
 - o paragraph below "2) The graph boundaries"
- the description of the linked-list and the connexions between arcs and nodes
 - o paragraph below "3) Linked list of SWC"

3.1 SWC interface

The SWC have a single entry point in the format "func (int, *,*,*)". The first parameter is the execution command (memory request, reset, set parameters, run, stop). The SWC can call CMSIS-Stream through a dedicated function pointer provided at reset time. An example of SWC API here.

3.1.1 SWC parameter "MEMREQ"

The first operation asked by the scheduler is to ask the SWC for memory allocation with respect to parameters associated to the input and output stream format (the SWC may ask for working memory buffer size in relation with the frame size of the streams).

A SWC delivered in source-code, or as library object using the same compilation tool chain as the application, can use memory allocation function from the standard C library (malloc(), realloc(), calloc()), and will have to manage the "free()" deallocation upon reception of the command "STREAM_END".

The format is: func (STREAM_MEMREQ, *ptr1, *ptr2, *ptr3):

- The first pointer is a memory space of 7 words of 32bits. The SWC will fill this area with up to 6 memory allocation requests terminated with "0". Each word is a bit-field (description in "A.4 Memory types") giving the size of the memory buffer, the byte alignment and the recommended speed. The memory can be declared "static" or "working" (or "scratch memory area"), depending if the content needs to be preserved between two calls. The first memory request is the "instance", which holds pointers to static and working memory buffers. The pointer to this memory area is reused in all the other SWC commands.
- The second parameter is pointing to a table of the stream formats used (see "A.3 Stream digital "data formats""). This information (buffer size, sampling rate, interleaving scheme) can be used by the SWC to adjust the request to the minimum amount of memory.
- The last parameter is TBD and reserved for a SWC activation protocol with key exchanges

3.1.2 SWC parameter "RESET"

The second operation of the scheduler is to provide the SWC with the memory being allocated.

The format is: func (STREAM_RESET, *ptr1, *ptr2, *ptr3):

- The first parameter points to the SWC instance, with memory allocation corresponding to the first word of the STREAM_MEMREQ. The following data is a vector of pointers corresponding the memory allocation requested in the same following order provided by the STREAM_MEMREQ.
- The second parameter is a pointer to the entry point of CMSIS-Stream, and giving access to optional services in computing, signal compression. There is a protocol *TBD* to activate this link: the SWC will use a single subroutine as calling address and will register the return address (seen by CMSIS-Stream) with a dummy call during this initialization sequence.
- The last parameter is unused.

3.1.3 SWC parameter "SET PARAMETER"

CMSIS-Stream is setting the SWC parameter at reset time with the default reset parameter vector provided in its manifest. This API allows to change a single parameter or the full set.

The format is: func (STREAM_SET_PARAMETERS, *ptr1, *ptr2, *ptr3):

- The first parameter "ptr1" points to the SWC instance.
- The second parameter points to the parameters to be updated
- The last parameter will be casted to integer and the LSB 9 bits tell the index or the tag used by the SWC documentation to change one parameter. The value 256 tells the full parameter list will be set.

The scheduler has no way to decide to change a parameter during the execution of the graph. The **Scripts** are used for this purpose.

3.1.4 SWC parameter "READ_PARAMETER"

The scheduler is reading the SWC parameter at reset time with the default reset parameter vector provided in its manifest. This API allows to change a single parameter or the full set.

The format is: func (STREAM_READ_PARAMETERS, *ptr1, *ptr2, *ptr3):

- The first parameter "ptr1" points to the SWC instance.
- The second parameter points to the parameters to be updated
- The last parameter will be casted to integer and the LSB 9 bits tell the index or the tag used by the SWC documentation to change one parameter. The value 256 tells the full parameter list will be set.

0

3.1.5 SWC parameter "RUN"

The scheduler launches the execution of the SWC when the conditions, found in the linked-list fields (processor architecture, arc's ready-flags) are set. The stream of data from the arcs are exchanged in the format detailed in the SWC manifest (see "A.3.1 Data format fields common to all streams").

The calling format is: func (STREAM_RUN, *ptr1, *ptr2, *ptr3).

As previously "ptr1" is the instance pointer of the component. "ptr2" is a pointer to a structure.

The "*ptr2" field points to a structure : [{data pointer stream1} {data pointer stream2} ..]

The "*ptr3" field points to a similar structure: [{parameter of stream1} {parameter of stream2}..]

Simple components have two streams: one as input, the other as output other can have up to 4 streams (several input/output combinations).

A data buffer is combination of a pointer and size. For input streams the size is the amount of data in the buffer. For output streams this is the amount of free space in the output buffer starting from the pointer address,

The SWC is updating the base address pointers and data sizes before returning to caller.

When a stream data format is **FMT_INTERLEAVED**, (for example Left and Right audio samples are in this order: LRLRLRLRLRLR...) then {data stream} is a pointer to the base address, {parameter stream} is the number bytes in the buffer

When a stream data format is **FMT_DEINTERLEAVED_1PTR**, (for example Left and Right audio samples are in this order: LLLL..LLLLRRRR...RRRR) the size of the first buffer (the "frame") then {data stream} is a pointer to the base address, {parameter stream} is the number bytes for a single frame (the size of the Left sample portion). The SWC will address the second and following channels by incrementing the base pointer address with the size of the frame. When a stream data format is **FMT_DEINTERLEAVED_NPTR**. The buffers have independent positions (for example color planes of images). The {data stream} is a combination of the pointer to the base address, and the size of the corresponding buffer. {parameter stream} is unused. For example with stereo audio: {data stream} points to a structure: [{*ptr_L, size L}, {*ptr_R, size R}], this is the format used in **EEMBC-audiomark**.

3.1.6 SWC parameter "END"

This command is used to free the allocated memory. The format is: func (STREAM_END, instance pointer, 0, 0).

3.2 ARCs descriptors

Two types of arcs are used in the graph: simple linear buffers and ring buffers. Simple arcs are described with two words of 32bits, Ring descriptors are using 6 words (the first 2 words are identical to the ones of simple arcs) with the purpose of managing complex situation with peripherals, multiprocessing, drift compensations, data monitoring. Ring buffers are used at the boundary of the graph, their content is realigned to the base address to avoid the SWC to manage folding addresses. The data format is:

- Word 0: 27 bits for the buffer base address and 5bits for the data format
 - The base address is computed in 3 sub-fields of a linear 22bits address shifted with an exponent of E = 2bits and 3bits selecting one of the 7 memory banks (see "1.1.2 processor characteristics"). Each CMSIS-Stream instance (see "Two entry points b) STREAM_RESET") has its table of offset to physical memory banks. The base address value is physical_address[offset] + (linear address << (E<<2)).</p>
 - The 5bits data format field is a compact way to give the data format details (see "A.3.1 Data format fields common to all streams") which is 128bits long. This data is an index to the table of data formats used in the graph. This table is part of the shared binary graph structure.
- Word 1: 24bits buffer size, 2bits to select the arc type, 8 bits for debug
 - o The buffer length is computed with a 22bits linear address and a 2 bits shifter to extend the length.
 - The 2 bits selector give the indication of linear or ring descriptor format
 - For debug, 4bits are ging the debug task to proceed, and 4 bits to select the debug register of the result.
 The debug register array is in the shared binary graph structure. The debug tasks are TBD and could be: estimation of the data rate, the time-stamp of the last acces, the peak / min / absmax data values with different forgetting factors.
- Word 2: read index on 24bits, flow management on 4bits, data alignment decision bit
 - The read index is a plain 24bit index in Bytes, and allows to manage 16MB buffers
 - There are 2bits for underflow and 2bits for overflow management during read/write access. The decision thresholds ("crumb in", "crumb out") are given in the Word-3. The underflow options are : repeat last

frames, generate zeroes (default), extrapolate last frame. The overflow options are : skip last frame, interpolate last frame.

0

- o To avoid data to fold when the write pointer is too close to the top of the buffer a data realignement will be proceeded based on a selection of '0' the crumb-in threshold, '1' the crumb-out threshold.
- Word 3: write index on 24bits, 4 bits of crumb_in, crumb_out
 - The write index is a plain 24bit index in Bytes. Buffer full condition corresponds to (W-R) = (Size-1).
 - o Crumb_in (2bits) is used to set the "ready flag" (see "3) Linked list of SWC") of the consumer SWC when the amount of data in the buffer is either larger the buffer size /2 /4 /8 /16.
 - Crumb_out (2bits) is used to set the "ready flag" (see "3) Linked list of SWC") of the producer SWC when the amount of free area in the buffer is either larger the buffer size /2 /4 /8 /16.
- Word 4: offset (19 bits) to the linked-list header of the SWC consumer of this arc.
- Word 5: Debug address field (27bits, format of the base address)

A Data types

A.1 Raw data types

Sample of raw data type <u>here</u>.

A.2 Array of Raw data types

When the raw data type is null, the next byte is the raw data type and the next 2 bytes are the number of raw data as array.

A.3 Stream digital "data formats"

The description of a full data format is made on 16 Bytes (4 words of 32bits): 8 Bytes for the digital format (frame-size, data interleaving, the raw data format in the frame, the number of channels, the sampling rate..) and 8 Bytes for domain-specific data format and mixed-signal sensor/transducer peripheral control.

A.3.1 Data format fields common to all streams

The first word of the common data format has the fields:

- Frame size in Bytes, on 24bits, allowing data frames of 16MB. The value 0 means "any size". SWC manifests are
 using the data format to for each of their input and output ports. In this case, the field "frame size" means the
 minimum of input data needed by the SWC before any processing is feasible. And for the output ports: the
 minimum of free area to have in the output buffer to avoid overflow due to the data being produced by the
 SWC.
- Interleaving scheme, on 2 bits, three options being used:
 - o "FMT_INTERLEAVED": data is interleaved within the frame, in sequence. For example left and right audio samples are found like "LRLRLRLR.." or gyroscope data is provided like "XYZXYZXYZ.."
 - o "FMT_DEINTERLEAVED_1PTR": interleaved format of frame-size ("LLLLLRRRRR LLLLLRRRRRR..")
 - "FMT_DEINTERLEAVED_NPTR": the data addressed with pairs of pointers and frame-size, the buffer do not need to be contiguous.
- Raw data format, on 6 bits, see "A.1 Raw data types".

The second word of the common data format has the fields:

- Number of channels minus one, on 5 bits, allowing up to 32 channels.
- Sampling rate, on 21 bits, the value 0 means "asynchronous or slave IO port". The data format is F=M x 2**E. With 19 bits for the unsigned mantissa "M", 2 bits for the exponents (values of "E" = 0,-8,-16,-24), allowing to set the rate from 1 week period up to 524kHz, with all the common audio and voice sampling rate with full accuracy.
- Time-stamp format, on 2bits:
 - No timestamp on the data frames
 - Absolute value of the time (64bits) on each frame, 2 MSB to control the format, 40 bits counting the SYSTICK periods of 1ms, 16 bits computed from SYST_RVR to have the fraction of 1ms.
 - Relative time from last frame (32 bits), 30bits of data and 2 MSB to control the format (0: seconds spent from reset, 1: seconds spent from January 1st 2023, 2: seconds interval in U14.16 format, 3: seconds interval in U24.4 format).
- Four bits unused

A.3.2 Domain-specific stream data format

The third word of the domain-specific data format has the fields:

Domain code on 6 bits

• Data mapping of the channels on 24 bits. Example of 7.1 format audio format (8 channels) FrontLeft, FrontRight, FrontCenter, LowFrequency, BackLeft, BackRight, SideLeft, SideRight. The code 0101b of a 2-channel stream, means data for FrontLeft and FrontCenter.

- Direction of the flow, 1 bit, "0" means data flow sent to the graph and "1" means generated by the graph processing
- Hashing of the stream, TBD